



LibreOffice
Community



Draw Guide 7.4

Chapter 3, Working with Objects

Copyright

This document is Copyright © 2023 by the LibreOffice Documentation Team. Contributors are listed below. This document maybe distributed and/or modified under the terms of either the GNU General Public License (<https://www.gnu.org/licenses/gpl.html>), version 3 or later, or the Creative Commons Attribution License (<https://creativecommons.org/licenses/by/4.0/>), version 4.0 or later. All trademarks within this guide belong to their legitimate owners.

Contributors

Contributors for this edition:

Peter Schofield

Contributors for previous editions:

Claire Wood
Dave Barton

Elzett Kotze
Jean Hollis Weber

John A Smith
Kees Kriek

Martin Fox
Peter Schofield

Feedback

Please direct any comments or suggestions about this document to the Documentation Team mailing list: loguides@community.documentfoundation.org.

Note

Everything sent to a mailing list, including email addresses and any other personal information that is written in the message, is publicly archived and cannot be deleted.

Publication date and software version

Published January 2023. Based on LibreOffice 7.4 Community.
Other versions of LibreOffice may differ in appearance and functionality.

Using LibreOffice on macOS

Some keystrokes and menu items are different on macOS from those used in Windows and Linux. The table below gives some common substitutions used in this document. For a detailed list, see LibreOffice Help.

| <i>Windows or Linux</i> | <i>macOS equivalent</i> | <i>Effect</i> |
|---|---|-------------------------------------|
| Tools > Options menu selection | LibreOffice > Preferences | Access setup options |
| Right-click | <i>Control</i> +click, <i>Ctrl</i> +click, or right-click depending on computer setup | Open a context menu |
| <i>Ctrl</i> or <i>Control</i> | ⌘ and/or <i>Cmd</i> or <i>Command</i> , depending on keyboard | Used with other keys |
| <i>Alt</i> | ⌥ and/or <i>Alt</i> or <i>Option</i> depending on keyboard | Used with other keys |
| <i>F11</i> | ⌘+T | Open the Styles deck in the Sidebar |

Contents

| | |
|---|-----------|
| Copyright..... | 2 |
| Contributors..... | 2 |
| Feedback..... | 2 |
| Publication date and software version..... | 2 |
| Using LibreOffice on macOS..... | 2 |
| Introduction..... | 5 |
| Selecting objects..... | 5 |
| Direct selection..... | 5 |
| Selection by framing..... | 5 |
| Selecting hidden objects..... | 5 |
| Arranging objects..... | 6 |
| Positioning and adjusting objects..... | 6 |
| Using zoom..... | 6 |
| Status bar..... | 7 |
| Zoom & View Layout dialog..... | 7 |
| Zoom toolbar..... | 8 |
| Moving and adjusting object size..... | 9 |
| Moving objects..... | 9 |
| Adjusting object size..... | 10 |
| Modifying arcs..... | 10 |
| Rotating and slanting objects..... | 10 |
| Rotating objects..... | 10 |
| Slanting objects..... | 11 |
| Setting exact position, size, rotation and slant..... | 12 |
| Position and Size..... | 14 |
| Rotating objects..... | 15 |
| Slant and corner radius..... | 16 |
| Using grid and snap functions..... | 17 |
| Configuring grid and snap functions..... | 17 |
| Snap to grid..... | 19 |
| Using Snap to Grid..... | 19 |
| Displaying grid..... | 19 |
| Changing color of grid points..... | 19 |
| Snap points and lines..... | 19 |
| Inserting snap points and snap lines..... | 20 |
| Displaying snap points and lines..... | 21 |
| Editing snap points and lines..... | 21 |
| Deleting snap points and lines..... | 22 |
| Configuring snap range..... | 22 |
| Using Helplines..... | 22 |
| Changing object shape..... | 23 |
| Regular shapes..... | 23 |
| Basic shapes..... | 23 |
| Symbol Shapes..... | 24 |
| Block Arrows..... | 25 |
| Callouts..... | 26 |

| | |
|---|----|
| Stars and Banners..... | 26 |
| Curves and polygons..... | 27 |
| Bézier curves..... | 27 |
| Converting objects to curve or polygon..... | 27 |
| Editing points..... | 27 |
| Point types..... | 28 |
| Tangents..... | 29 |
| Symmetric transition..... | 30 |
| Smooth transition..... | 30 |
| Corner point..... | 30 |
| Points..... | 31 |
| Moving points..... | 31 |
| Inserting points..... | 32 |
| Deleting points..... | 32 |
| Eliminating points..... | 33 |
| Converting curves or lines..... | 33 |
| Splitting objects..... | 34 |
| Closing objects..... | 34 |
| Distorting objects..... | 35 |

Introduction

This chapter looks at the tools and functions to modify existing drawings. All of the functions apply to a selected object or a group of selected objects, which can be distinguished by selection handles on a rectangular frame that is large enough to contain the object. Where several objects are selected, the frame around the objects corresponds to the smallest rectangle that can contain all of the objects. This frame is called the selection rectangle.

✓ Note

The color and shape of the selection handles changes depending on the tool and function that has been selected to change the object properties. The color of the selection handles also depends on the computer operating system and how the computer has been set up.

Selecting objects

Direct selection

The easiest way to select an object is to click directly on it. For objects that are not filled, click on the object border to select it. To select more than one object, hold the *Shift* key down while clicking on objects. To deselect an object, move the cursor into a blank space and click.

Selection by framing

Several objects can be selected at once by clicking and dragging the cursor around the objects drawing a selection rectangle around the objects. Only objects that lie entirely within this selection rectangle are selected. To select multiple objects by framing, **Select** on the Drawing toolbar must be active, as shown in Figure 1.



Figure 1: Drawing toolbar

Selecting hidden objects

If objects are located behind others and not visible, they can still be selected. When a hidden object is selected, its selection handles appear through the objects covering it.

- **Windows, Mac or Linux** — press the *Tab* key to select and cycle through the selection of objects in a drawing, stopping at the hidden object to select it. To cycle through the objects in reverse order, press *Shift+Tab*.

- **Windows or Mac only** — select the object in front of a hidden object, then press the *Alt* key (macOS \backslash) and click to select the hidden object. If there are several hidden objects, keep holding down the *Alt* key (macOS \backslash) and clicking until the object required is reached. To cycle through the objects in reverse order, hold down the *Alt+Shift* keys (macOS \backslash +*Shift*) and click.

Arranging objects

In a complex drawing, several objects may be stacked on top of one another. This stacking order can be rearranged by moving an object forward or backward using one of the following methods:

- Select an object, go to **Shape > Arrange** on the Menu bar, or right-click on the object and select **Arrange** from the drop down menu, then select one of the following options:
 - **Bring to Front** (*Ctrl+Shift++*) (macOS $\text{⌘}+Shift++$)
 - **Bring Forward** (*Ctrl++*) (macOS $\text{⌘}++$)
 - **Send Backward** (*Ctrl+-*) (macOS $\text{⌘}+-$)
 - **Send to Back** (*Ctrl+Shift+-*) (macOS $\text{⌘}+Shift+-$)
 - **In Front of Object**
 - **Behind Object**
- Select an object, then select one of the **Arrange** tools at the left end of the Line and Filling toolbar (Figure 2). When the cursor hovers over a tool, its function is indicated.




Figure 2: Line and Filling toolbar

Positioning and adjusting objects

Using zoom

To help in the positioning and adjustment of objects, Draw has a zoom function that reduces or enlarges the screen display of the current drawing. For example, zoom in to position objects on a drawing with greater accuracy; zoom out to see the complete drawing. Zooming is controlled using the **Status Bar**, Zoom & View Layout dialog, or Zoom toolbar.

✓ Note

Zooming is handled differently in Linux operating systems. Drawings saved with 100% zoom factor in Windows or macOS are displayed at a larger zoom factor in Linux.




Figure 3: Status Bar zoom controls

- | | |
|--------------------------------|-----------------------|
| 1) Fit slide to current window | 2) Zoom slide control |
| | 3) Zoom percentage |




Figure 4: Zoom & View Layout dialog

Status bar

The zoom controls are located on the right side of the **Status Bar** (Figure 3) and these controls give quick and easy access to zooming. Use one of the following methods to change the zoom factor:

- **Fit slide to current window** – fits the drawing to the open window.
- **Zoom Out** — minus sign (–) on the zoom slide control reduces the zoom factor.
- **Zoom In** — plus sign (+) on the zoom slide control increases the zoom factor.
- Click and drag the zoom slide control to increase or decrease the zoom factor.
- Right-click on the zoom percentage number and select a zoom option from the context menu that opens.

Zoom & View Layout dialog

The Zoom & View Layout dialog (Figure 4) is opened using one of the following methods:

- Click on the zoom percentage number in the **Status Bar**.
- Go to **View > Zoom > Zoom** on the Menu bar.

The Zoom & View Layout dialog provides the following options to control how a drawing is viewed on a display.

Zoom Factor

Sets the zoom factor at which to display the current document and all documents of the same type that are subsequently opened.

Optimal

Resizes the display to fit the width of the text in the document.

Fit width and height

Displays the entire page on the screen.



Figure 5: Zoom toolbar

Fit width

Displays the complete width of the document page. The top and bottom edges of the page may not be visible.

100%

Displays the document at its actual size.

Variable

Enter a percentage in the box for the zoom factor to display the document.

View Layout

Used to set the view layout and is not available for drawings. View layout is normally used in text documents to see the effects of different layout settings.

Zoom toolbar

Go to **View > Toolbars > Zoom** on the Menu bar to open the Zoom toolbar (Figure 5). The tools available on this toolbar, from left to right, are as follows:

Zoom In

Displays the drawing at two times its current size each time the tool is selected.

Zoom Out

Displays the drawing at half its current size each time the tool is selected.

100%

Displays the drawing at its actual size.

Zoom Previous

Returns the display of the drawing to the previous zoom factor applied.

Zoom Next

Undo the action of the previous zoom command.

Entire Page

Displays the whole drawing in the **Workspace**.

Page Width

Displays the complete width of the drawing. The top and bottom edges of the slide may not be visible.

Optimal

Resizes the display to include all of the objects on the slide.

Object Zoom

Resizes the display to fit the selected object(s).

Zoom & Pan

Zooms in for each click. *Ctrl+click* (macOS *⌘+click*) zooms out for each click. *Shift+click* allows panning of the drawing.

Shift

Moves the drawing within the **Workspace**. Place the cursor on the drawing and drag to move the drawing.

Moving and adjusting object size

When moving an object or changing its size, check the left-hand area of the **Status Bar** at the bottom of the **Workspace** (Figure 6). From left to right, this area shows that a shape is selected, its position on the drawing in X/Y coordinates and dimensions of the object. The measurement units are those selected in **Tools > Options > LibreOffice Draw > General** (macOS **Preferences > LibreOffice > LibreOffice Draw > General**).

Moving objects

To move an object (or a group of objects), select it, then click and drag within the object borders. During movement, a ghost image of the object appears to help with repositioning, as shown in Figure 7. When the object reaches its new location, release the cursor.




Figure 6: Left end of Status Bar with object selected




Figure 7: Example of moving objects




Figure 8: Example of adjusting objects

Adjusting object size

To change the size of a selected object (or a group of selected objects), move the cursor to one of the selection handles. The cursor changes shape to indicate the direction of movement for that selection handle.

Click and drag the selection handle to change object size. The results depend on which selection handle is used. To resize an object along one axis, use a side, top, or bottom handle. To resize along both axes, use a corner handle.

As the object size changes, a ghosted outline of the object appears, as shown in Figure 8. When the desired size of the object is reached, release the cursor.

✓ Note

Pressing and holding the *Shift* key while resizing an object. changes the size symmetrically keeping the aspect ratio of width to height the same. This *Shift* key behavior works on all selection handles.

Modifying arcs

The size of an arc can be changed by adjusting the positions of the start and end points of an arc. The selection handle at the start point of an arc is larger than the end point of an arc.

Select an arc, then right click on the arc and select **Points** from the drop down menu or press the *F8* key. Two handles appear at the start and end of the arc, as shown in Figure 9.

Click and drag on one of the start or end handle to change the shape of the arc. Release the cursor when the desired arc shape is reached.

Rotating and slanting objects

Rotating objects

To rotate an object (or a group of objects), select the object, then go to rotation mode using one of the following methods.

- 1) Select an object so that the selection handles are displayed.




Figure 9: Example of modifying arcs




Figure 10: Object in rotation mode




Figure 11: Transformations toolbar

- 2) Use one of the following methods to switch to rotation mode. The selection handles change shape and color and a center of rotation indicator appears in the center of the object, as shown in Figure 10.
 - Click again on a selected object.
 - Click on the triangle ▼ on the right of **Transformations** on the Line and Filling toolbar and select **Rotate** from the pop up menu.
 - Go to **View > Toolbars > Transformations** on the Menu bar to open the Transformations toolbar (Figure 11) and select **Rotate**.
- 3) Move the cursor over a corner selection handle and the cursor changes shape to indicate rotation mode.
- 4) Click on and drag the corner selection handle to rotate the object. Release the cursor when the desired object rotation is reached.

✓ Notes

The rotation center is normally located at the center of an object. To change the position of the rotation center, click and drag the rotation center until it is at the desired position. This rotation center can even be outside of the object.

Rotation works in a slightly different way for 3D objects because it occurs in a three dimensional space and not in a single plane. See Chapter 7, Working with 3D Objects for more information.

Slanting objects

The axis used for slanting an object is the object edge directly opposite the midpoint handle being used to slant the object. This axis stays fixed in location while the other sides of the object move in relation to it as the selection handle is dragged. In Figure12 the selection handle at the bottom of the object has been used to slant the object..




Figure 12: Example of slanting objects

- 1) Select or click on an object and use one of the following methods to switch to rotation mode. The selection handles change shape and color and a center of rotation indicator appears in the center of the object.
 - Click again on a selected object.
 - Click on the triangle ▼ on the right of **Transformations** on the Line and Filling toolbar and select **Rotate** from the pop up menu.
 - Go to **View > Toolbars > Transformations** on the Menu bar to open the Transformations toolbar and select **Rotate**.
- 2) Move the cursor over a selection handle at the midpoint of the top, bottom, left or right sides of the object and the cursor changes shape to indicate slanting direction.
- 3) Click and drag the selection handle to slant the object. Release the cursor when the desired object slant is reached. A ghosted outline of the object being slanted appears and the current angle of slanting is shown in the **Status Bar**.

✓ Note

Press and hold the *Shift* key while rotating or slanting an object, movement is restricted to 15°. This is the default behavior of the *Shift* key. However, if **When creating or moving objects** has been selected in **Tools > Options > LibreOffice Draw > Grid** (macOS **LibreOffice > Preferences > LibreOffice Draw > Grid**), the action of the *Shift* key is reversed and rotation or slanting is restricted to 15° of movement unless the *Shift* key is pressed.

Setting exact position, size, rotation and slant

Using the cursor to position and resize objects is not exact. If greater accuracy is required to position and size an object, it is recommended to use the Position and Size dialog (Figure 13), or the **Position and Size** panel (Figure 14) in the Properties deck on the Sidebar.

- To open the Position and Size dialog, select the object and use one of the following methods:
 - Go to **Format > Position and Size** on the Menu bar.
 - Right-click on the object and select **Position and Size** from the context menu.
 - Use the keyboard shortcut *F4*.
- To open the **Position and Size** panel in the Properties deck on the Sidebar, select the object, then click on **Properties** on the Sidebar and click on the chevron > on the **Position and Size** title bar to open the panel.




Figure 13: Position and Size dialog




Figure 14: Position and Size panel in Properties deck on Sidebar

Position and Size

Position

Specify the location of the selected object on the page. The units of measurement used for X/Y coordinates and the width and height of the object are set by going to **Tools > Options > LibreOffice Draw > General** (macOS **LibreOffice > Preferences > LibreOffice Draw > General**).

Position X

Enter the horizontal distance required to move the object relative to the base point selected in the grid.

Position Y

Enter the vertical distance required to move the object relative to the base point selected in the grid.

Base point

Select a base point in the grid and then enter the amount required to shift the object relative to the base point that is selected in the *Position Y* and *Position X* boxes. The base points correspond to the selection handles on an object. This option is only available in the Position and Size dialog.

Size

Specify the amount required to resize the selected object with respect to the selected base point.

Width

Enter a width for the selected object.

Height

Enter a height for the selected object.

Keep ratio

Maintains proportions when resizing the selected object.

Base point

Select a base point in the grid, and then enter the new size dimensions for the selected object in the *Width* and *Height* boxes. This option is only available in the Position and Size dialog.

Protect

This option is only available in the Position and Size dialog.

Position

Prevents changes to the position or the size of the selected object.

Size

Prevents resizing of the object.

Adapt

Specifies, if the size of a text box should be adjusted to fit the size of entered text. This option is only available in the Position and Size dialog for text boxes.

Fit width to text

Expands the width of the object to the width of the text, if the object is smaller than the text.

Fit height to text

Expands the height of the object to the height of the text, if the object is smaller than the text.

✓ Note

The default location of the base points for position and size is the upper left corner of the drawing area. This base point can be temporarily changed to make positioning or dimensioning simpler by clicking on a position corresponding to the location of the base point required. This change in base point is only valid for single use and the base point is reset to the standard position of top left corner when the Position and Size dialog is closed.

Rotating objects

To accurately rotate an object, click on the **Rotation** tab of the Position and Size dialog to open the **Rotation** page (Figure 15). The options available allow the rotation angle and the location of the pivot point to be defined. Alternatively, use the available options for rotation in the **Position and Size** panel in the Properties deck on the Sidebar.

Pivot Point

The selected object is rotated around a specified pivot point and is only available in the Position and Size dialog. The default position for the pivot point is at the center of the object. The pivot point can be moved from its default central position by changing the setting for *Position X* and/or *Position Y*, or selecting a position in *Default settings*.

Position X

Enter horizontal distance from the left edge of the page to change the position of the pivot point.

Position Y

Enter vertical distance from the top edge of the page to change the position of the pivot point.

Default settings

Select the position of the pivot point. Default position is the center of the object.

Changing the pivot point is valid for single use only and is reset to the default central position when the Position and Size dialog is closed.

Rotation Angle

Specify the number of degrees required to rotate the selected object. This option is only available in the Position and Size dialog.




Figure 15: Position and Size dialog - Rotation page




Figure 16: Position and Size dialog - Slant & Corner Radius page

Angle

Enter the number of degrees that required to rotate the selected object.

Default settings

Click on the indicator to rotate the object. The number of degrees rotated is shown in the *Angle* box.

Slant and corner radius

To accurately set the corner radius or slant angle of an object, click on the **Slant & Corner Radius** tab of the Position and Size dialog (Figure 16). Options for slant and corner radius are only available in the Position and Size dialog.

Corner Radius

This option is only available for the corners of a rectangular or square object that has been created using the Legacy Rectangles toolbar. This toolbar is optional and is opened by going to **View > Toolbars > Legacy Rectangles** on the Menu bar. If this option is grayed out, the corner radius cannot be set.

Radius

Enter the radius of the circle that is to be used to round corners. The larger the value for corner radius set, the rounder corners of a rectangle or square become.

Slant

Slants the selected object along the bottom edge of the object.

Angle

Enter the angle of the slant axis. The slant angle relates to how much an object inclines or slants from its normal vertical position on a drawing.

Control Point 1/Control Point 2

These control points are special handles or dots that are available on some shapes and are used to change the properties of a shape. If these options are grayed out, then the shape does not have a special handle and coordinates cannot be set.

Enter a value to set the X and Y coordinates of the special handle in relation to the top left corner of the shape. The example shown in Figure 17 shows the change in shape after adjusting the X coordinate of Control Point 1 of the special handle.

✓ Note

For more information on this special handle used for control points, see “Changing object shape” on page 23.




Figure 17: Example of Corner Point adjustment




Figure 18: Options LibreOffice Draw dialog - Grid page



Figure 19: Options toolbar

Using grid and snap functions

Objects can be positioned accurately and consistently using the grid and snap functions available in Draw. To make it easier to use the grid and snap functions, it is recommended to use the highest practical zoom value for a drawing. Two different functions can be used at the same time. For example, snapping to a guide line and the page edge. However, it is recommended to activate only those snap functions that are necessary.

Configuring grid and snap functions

To configure the grid and snap functions in a drawing, go to **Tools > Options > LibreOffice Draw > Grid** (macOS **LibreOffice > Preferences > LibreOffice Draw > Grid**) on the Menu bar to display the Grid dialog (Figure 18). The grid and snap functions can also be displayed and switched on or off using this dialog, right-clicking on a drawing and selecting options in the context menu, or using the tools on the Options toolbar (Figure 19). If the Options toolbar is not open, go to **View > Toolbars > Options** on the Menu bar.

Grid

Specifies the settings for the configurable grid in a drawing and helps to determine the exact position of objects. Also, this grid can be set in line with the magnetic snap grid. If the snap grid is activated, but want to move or create individual objects without snap positions, keep the *Shift* key pressed to deactivate this function.

Snap to grid

Specifies whether to move frames, drawing elements, and controls only between grid points. To change the status of the snap grip only for the current action, drag an object while holding down the *Ctrl* key (macOS ⌘).

Visible grid

Specifies whether to display the grid.

Resolution

Horizontal

Defines the unit of measure for the spacing between grid points on the X-axis.

Vertical

Defines the grid points spacing in the desired unit of measurement on the Y-axis.

Synchronize axes

Specifies whether to change the current grid settings symmetrically. The resolution and subdivision for the X and Y axes remain the same.

Subdivision

Horizontal

Specify the number of intermediate spaces between grid points on the X-axis.

Vertical

Specify the number of intermediate spaces between grid points on the Y-axis.

Snap

To snap lines

Snaps the edge of a dragged object to the nearest snap line when the click is released. This setting can also be defined using **Snap to Snap Guides** on the Options toolbar.

To the page margins

Specifies whether to align the contour of the graphic object to the nearest page margin. The cursor or a contour line of the graphics object must be in the snap range. This function can also be accessed using **Snap to Page Margins** in the Options toolbar.

To object frame

Specifies whether to align the contour of the graphic object to the border of the nearest graphic object. The cursor or a contour line of the graphics object must be in the snap range. This function can also be accessed with **Snap to Object Border** in the Options toolbar.

To object points

Specifies whether to align the contour of the graphic object to the points of the nearest graphic object. This only applies if the cursor or a contour line of the graphics object is in the snap range. This function can also be accessed with **Snap to Object Points** in the Options toolbar.

Snap range

Defines the snap distance between the cursor and the object contour. Snaps to a snap point if the cursor is closer than the distance selected.

Constrain Objects

When creating or moving objects

Specifies that graphic objects are restricted vertically, horizontally or diagonally (45°) when creating or moving them. This setting can be temporarily deactivated by pressing the *Shift* key.

Extend edges

Specifies that a square is created based on the longer side of a rectangle when the *Shift* key is pressed before releasing the click. This also applies to an ellipse (a circle is created based on the longest diameter of the ellipse). When *Extend edges* is not selected, a square or a circle is created based on the shorter side or diameter.

When rotating

Specifies that graphic objects can only be rotated within the rotation angle that is selected. To rotate an object outside the defined angle, press the *Shift* key when rotating. Release the key when the desired rotation angle is reached.

Point reduction

Defines the angle for point reduction. When working with polygons, this maybe useful in reducing the editing points.

Snap to grid

Using Snap to Grid

Using **Snap to Grid** moves an object exactly onto a grid point in a drawing. This function can be switched on and off using one of the following methods:

- Go to **View > Snap Guides > Snap to Grid** on the Menu bar.
- Right-click on a drawing and select **Snap Guides > Snap to Grid** from the context menu.
- Click on **Snap to Grid** on the Options toolbar.

Displaying grid

Displaying or turning off the grid in a drawing is done using one of the following methods:

- Go to **View > Grid and Helplines > Display Grid** on the Menu bar.
- Click on **Display Grid** on the Options toolbar.
- Right-click on a drawing and select **Grid and Helplines > Display Grid** from the context menu.
- Select **Visible grid** in the Options LibreOffice Draw Grid dialog.

Changing color of grid points

By default and depending on the display and computer setup, the grid points are gray and are not always easy to see. To change the color of the grid points, go to **Tools > Options > LibreOffice > Application Colors** (macOS **LibreOffice > Preferences > LibreOffice > Application Colors**) to open the Application Colors dialog (Figure 20). In **Drawing/Presentation**, select a more suitable color for the grid from the drop-down list.

Snap points and lines

Unlike the grid, snap lines and snap points can be inserted when to position an object to a specific position on a drawing. Snap lines can either be horizontally or vertically and appear as dashed lines. Snap points appear as small crosses with dashed lines. Snap points and snap lines do not appear in printed output.




Figure 20: Options LibreOffice dialog - Application Colors page




Figure 21: New Snap Object dialog

Inserting snap points and snap lines

To insert a snap point or snap line, go to **Insert > Snap Guide** on the Menu bar to open the New Snap Object dialog (Figure 21).

Position

Sets the position of a selected snap point or line relative to the top left corner of the page.

X:

Enter the amount of space required between the snap point or line and the left edge of the page.

Y:

Enter the amount of space required between the snap point or line and the top edge of the page.

Type

Specifies the type of snap object being inserted.

Point

Inserts a snap point.

Vertical

Inserts a vertical snap line.

Horizontal

Inserts a horizontal snap line.

Displaying snap points and lines

Displaying or turning off snap points and lines in a drawing can be done using one of these methods:

- Go to **View > Snap Guides > Display Snap Guides** on the Menu bar.
- Click on **Display Snap Guides** in the Options toolbar.
- Right-click on a drawing and select **Snap Guides > Display Snap Guides** from the context menu.

Editing snap points and lines

To edit a snap point, right-click on the snap point and select **Edit Snap Point** from the context menu to open the Edit Snap Point dialog (Figure 22). Enter new X and Y coordinate settings for the snap point and click **OK**. Alternatively, click and drag a snap point to a new position on a drawing.

To edit a snap line, right-click on the snap line and select **Edit Snap Line** from the context menu to open the Edit Snap Line dialog (Figure 23). Enter a new X coordinate setting for vertical snap lines or a new Y coordinate setting for horizontal snap lines and click **OK**. Alternatively, click and drag a snap line to a new position on a drawing.




Figure 22: Edit Snap Point dialog




Figure 23: Edit Snap Line dialog

Deleting snap points and lines

To delete a snap point, drag it back to a ruler or right-click on the snap point and select **Delete Snap Point** from the context menu.

To delete a snap line, drag it back to the ruler or right-click on the snap line and select **Delete Snap Line** from the context menu.

Configuring snap range

To configure the snap range of when an object snaps to position

- 1) Go to **Tools > Options > LibreOffice Draw > Grid** (macOS **LibreOffice > Preferences > LibreOffice Draw > Grid**) on the Menu bar to open the Options LibreOffice Grid dialog.
- 2) Enter the number of pixels to set the proximity of when the object will snap into position in the *Snap range* box. The default setting is 5 pixels.
- 3) Click **OK** to set the new snap range and close the dialog.

Using Helplines

Helplines are a function in Draw to help in positioning of objects. Helplines can be displayed while the object is being moved. They extend from the edges of the object to the rulers at the top and left side of a drawing and do not have a snap function (Figure 24).

To use guide lines, go to **Tools > Options > LibreOffice Draw > View** (macOS **LibreOffice > Preferences > LibreOffice Draw > View**) on the Menu bar to open the Options LibreOffice Draw View dialog (Figure 25) and select *Helplines when moving* option or click *Helplines While Moving* in the Options toolbar.




Figure 24: Example of Helplines While Moving




Figure 25: Options LibreOffice Draw dialog - View page

Changing object shape

Regular shapes

When drawing certain regular shapes, one or more dots (special handles) are displayed in a different color to the selection handles when an object is selected. When the cursor hovers over one of these dots, it changes shape. Clicking and dragging on these dots modifies the shape of the object. For example, increasing corner radius of a rounded rectangle or square, changes the angles of an arc, and so on. These dots perform different functions according to the shape selected.

✓ Note

Regular shapes can also be changed after conversion to a curve or polygon and editing the points. See “Curves and polygons” on page 27 and “Editing points” on page 27 for more information.

Basic shapes

Refer to Figure 26, from left to right, to identify the following shapes with adjustment dots.




Figure 26: Basic Shapes sub-toolbar

Rectangle, Rounded

Changes the radius of the curve that replaces the angled corners of a rectangle or square.

Square, Rounded

Changes the radius of the curve that replaces the angled corners of a rectangle or square.

Parallelogram

Changes the internal angles between the sides.

Trapezoid

Changes the internal angles between the sides.

Circle Pie

Changes the size of the filled sector.

Block Arc

Changes both internal diameter and size of the filled area.

Isosceles Triangle

Changes the shape and type of the triangle.

Hexagon

Changes the internal angles between the sides.

Octagon

Changes the internal angles between the sides.

Cylinder

Changes the perspective.

Cube

Changes the perspective.

Folded Corner

Changes the size of the folded corner.

Cross

Changes the thickness of the four arms of the cross.

Frame

Changes the thickness of the frame.

Ring

Changes the internal diameter of the ring.

Symbol Shapes

Refer to Figure 27, from left to right, to identify the following shapes with adjustment dots.



Figure 27: Symbol Shapes sub-toolbar

Smiley Face

Changes the smile on the face.

Heart

Changes the shape of the symbol.

Sun

Changes the shape of the symbol.

Moon

Changes the shape of the symbol.

Prohibited

Changes the thickness of the ring and the diagonal bar.

Square Bevel

Changes the thickness of the bevel.

Octagon Bevel

Changes the thickness of the bevel.

Diamond Bevel

Changes the thickness of the bevel.

Double Bracket

Changes the curvature of the bracket.

Left Bracket

Changes the curvature of the bracket.

Right Bracket

Changes the curvature of the bracket.

Double Brace

Changes the curvature of the bracket.

Left Brace

Changes the curvature of the brace and the position of the point.

Right Brace

Changes the curvature of the brace and the position of the point.

Block Arrows

Refer to Figure 28, from left to right, to identify the following shapes with adjustment dots.




Figure 28: Block Arrows sub-toolbar

Right Arrow

Changes the shape and thickness of the arrow.

Left Arrow

Changes the shape and thickness of the arrow.

Down Arrow

Changes the shape and thickness of the arrow.

Up Arrow

Changes the shape and thickness of the arrow.

Left and Right Arrow

Changes the shape and thickness of the arrow.

Up and Down Arrow

Changes the shape and thickness of the arrow.

Circular Arrow

Changes the shape and thickness of the arrow.

4-way Arrow

Changes the shape and thickness of the arrow.

Chevron

Changes the angle between the sides and the shape.

Pentagon

Changes the angle between the sides and the shape.

Striped Right Arrow

Changes the shape and thickness of the arrow.

Up, Right and Down Arrow

Changes the shape and thickness of the arrow.

Notched Right Arrow

Changes the shape and thickness of the arrow.

Up and Right Arrow

Changes the shape and thickness of the arrow.

Right Arrow Callout

Changes the shape and thickness of the callout.

Left Arrow Callout

Changes the shape and thickness of the callout.

Down Arrow Callout

Changes the shape and thickness of the callout.

Up Arrow Callout

Changes the shape and thickness of the callout.

Left and Right Arrow Callout

Changes the shape and thickness of the callout.

Up and Down Arrow Callout

Changes the shape and thickness of the callout.

4-way Arrow Callout

Changes the shape and thickness of the callout.

Up and Right Arrow Callout

Changes the shape and thickness of the callout.

Callouts

For all callouts (Figure 29) use the adjustment dots to change the length, position and angle of the pointer.



Figure 29: Callouts sub-toolbar

Stars and Banners

Refer to Figure 30, from left to right, to identify the following shapes with adjustment dots.




Figure 30: Stars and Banners sub-toolbar

4-Point Star

Changes the thickness and shape of the star points.

8-Point Star

Changes the thickness and shape of the star points.

24-Point Star

Changes the thickness and shape of the star points.

Vertical Scroll

Changes the width and shape of the scroll.

Horizontal Scroll

Changes the width and shape of the scroll.

Doorplate

Changes the inward curvature of the corners.

Curves and polygons

Bézier curves

The editing of curves and polygons depends on the mathematics of Bézier curves¹. Explaining Bézier curves goes beyond this scope of this chapter. See Chapter 11, Advanced Draw Techniques for more information on drawing and manipulating Bézier curves.

Editing a Bézier curve consists in principle of moving points or tangents passing through these points. Each tangent has one control point at each end and a junction point where it meets the curve. The relative angle and distance between control points determine the shape of the curve. Figure 31 shows what happens to a basic square and changing only one point on the square.

Converting objects to curve or polygon

When changing the shape of an object and before modifying the points on an object, it must be converted to a curve or a polygon. Depending on what kind of shape and effect required to produce using one of the following methods to create a curve or a polygon:

- After selecting an object, go to **Shape > Convert** on the Menu bar and select either **To Curve** or **To Polygon**.
- Right click on an object and select **Convert > To Curve** or **To Polygon** from the context menu.

Editing points

Many different shapes can be created by moving either the point itself, or one or both of the round handle points at either end of the tangent, as shown in Figure 31. Points can be added, deleted, or points type changed using tools available on the Edit Points toolbar (Figure 32).

After converting a shape to a curve or polygon, object points are edited as follows:

- 1) Select the object and switch to points editing mode using one of the following methods.
 - Go to **Edit > Points** on the Menu bar.
 - Click on the **Points** tool on the Standard toolbar.
 - Right click on the converted object and select **Points** from the context menu.
 - Use the keyboard shortcut *F8*.




Figure 31: Example of creating different shapes by changing tangent points

1 Bézier curves were invented by Pierre Bézier, who developed the technique in the 1960s and while as an engineer with the Renault car manufacturer. The technology was intended to make modeling the surface of vehicles easier.



Figure 32: Edit Points toolbar

✓ Note

After switching to points editing mode, the selection handles become points. The number of points may increase or reduce in number. This change in number depends on the shape of the object and is normal behavior.

- 2) Click on an object point to change the object shape. The Edits Points toolbar opens and the tools become active when a point is selected. Tangents also appear attached to the selected point.
- 3) Use the various tools on the Edit Points toolbar to add, delete, or change the point type.
- 4) Click on and drag the point to move the point and change the object shape.
- 5) If the selected object is a curve, click on and drag the round points at the end of a tangent to make further changes to the object shape.
- 6) When satisfied with the shape, click outside of the object to cancel points editing mode and close the Edit Points toolbar.

Point types

The available tools on the Edit Points toolbar depend on the object and type of object point that has been selected.

Move Points

Activates a mode allowing movement of points. Click, hold and drag the selected point to another location. The object border follows the movement on both sides of the selected point to the next point on each side of the selected point.

Insert Points

Activates the insert mode and allows points to be inserted. Points can also be moved. A point is inserted onto the selected object each time there is a click made and the object changes shape to include the new point into the border of the object. The inserted point is a smooth point.

Delete Points

Used to delete points from the selected object. Select **Delete Points** and then click on a point to delete it. To delete several points, hold down the *Shift* key as each point is selected for deletion, then click on **Delete Points**.

Convert To Curve

Converts a curve into a straight line or a straight line into a curve. If a single point is selected, the curve before the point will be converted. If two points are selected, the curve between both points will be converted. If more than two points are selected and each time this icon is clicked, a different portion of the curve will be converted. If necessary, round points are converted into corner points and corner points are converted into round points.

If a section of the curve is a straight line, the end points of the line have a maximum of one control point each. They cannot be modified to round points unless the straight line is converted back to a curve.

Close Bézier

Closes a curve. A curve is closed by connecting the last point with the first point, indicated by an enlarged square.

Split Curve

Select the point or points where the curve will be split, then click on **Split Curve**.

Corner Point

Converts the selected point or points into corner points. Corner points have two movable control points, which are independent from each other. A curved line, therefore, does not go straight through a corner point, but forms a corner.

To create a corner point, a smooth or a symmetrical point must be inserted first and then converted to a corner point by clicking on **Corner Point**.

Smooth Transition

Converts a corner point or symmetrical point into a smooth point. Both control points of the corner point are aligned in parallel, and can only be moved simultaneously. The control points may differentiate in length, allowing variation in the degree of curvature.

Symmetric Transition

Converts a corner point or a smooth point into a symmetrical point. Both control points of the corner point are aligned in parallel and have the same length. They can only be moved simultaneously and the degree of curvature is the same in both directions.

Eliminate Points

Marks selected points for deletion. This happens if the point is located on a straight line. If converting a curve or a polygon using **Convert to Curve** into a straight line or alter a curve using the cursor so that a point lies on the straight line, the selected point is removed. The angle from which the point reduction is to take place is 15° by default.

Tangents

Before using tangents on an object, the object must be converted to a curve. Tangents are only used on curves. If an object has been converted to a polygon and a tangent is added, the object is automatically converted to a curve.

✓ Note

The angle that a tangent relates to an object shape can be changed by clicking on one of the tangent control points at the end of a tangent and moving it with the cursor. As the tangent angle is changed, the shape of the object changes in response.




Figure 33: Example of symmetric transition

Symmetric transition

Symmetric transition converts a corner point or a smooth point into a symmetrical point. The tangents have the same length and are aligned in a straight line, as shown in Figure 33. The tangents can only be moved simultaneously and the degree of curvature is the same in both directions.

- 1) Convert the object to a curve or polygon.
- 2) Switch the selected object into editing points mode and open the Edit Points toolbar.
- 3) Select the point to be changed to a symmetrical point.
- 4) Click on **Symmetric Transition** in the Edit Points toolbar. The straight line on each side of the symmetric transition point is converted to a curve.
- 5) Click and drag one of the tangent control handles to change the curvature and shape of the object. Any change to one tangent is carried over symmetrically to the other tangent.

Smooth transition

Smooth transition converts a corner point or symmetrical point into a smooth point. The tangents are aligned in a straight line and can only be moved simultaneously. The tangents can have different lengths with the curvature controlled by the longest tangent being the largest curvature, as shown in Figure 34.

- 1) Convert the object to a curve or polygon.
- 2) Switch the selected object into editing points mode and open the Edit Points toolbar.
- 3) Select the point to be changed to a symmetrical point.
- 4) Click on **Smooth Transition** on the Edit Points toolbar.
- 5) Click and drag one of the tangent control handles to change the shape of the object. This creates an asymmetric tangent with the largest curvature on the tangent longest side.




Figure 34: Example of smooth transition

Corner point

Converts a selected point or points into corner points. Corner points have two movable control points, which are independent from each other. It is possible to independently change the angle on each side of a tangent using the central point of the tangent as a corner point, as shown in Figure 35.

- 1) Convert the object to a curve or polygon.
- 2) Switch the selected object into editing points mode and open the Edit Points toolbar.




Figure 35: Example of corner point

- 3) Select the point to be changed to a symmetrical point.
- 4) Click on **Corner Point** on the Edit Points toolbar.
- 5) Click and drag the end of one of the tangents to change its angle. Each tangent can be moved independently to create spikes and troughs in an object shape.

Points

Moving points

When moving points, the object border on both sides of the point follows the movement of the point changing the object shape.

- 1) Convert the object to a curve or a polygon.
- 2) Switch the selected object into editing points mode and open the Edit Points toolbar.
- 3) Select the point to be changed to a symmetrical point.
- 4) Click on **Move Points** on the Edit Points toolbar.
- 5) Place the cursor on the selected point, then click and drag the point to create a new shape. Figure 36 illustrates how a different shape can be created from a circle by dragging the left hand side point to the left.




Figure 36: Example of moving points




Figure 37: Example of inserting points

Inserting points

A point is inserted onto the selected object each time there is a click. Clicking inside the border of the object, the object changes shape to include the new point into the border of the object, as shown in Figure 37. The inserted point is a smooth point.

Points can also be moved in insert point mode. Hover the cursor over the point until it changes shape, then click and drag the point to change the object shape.

- 1) Convert the object to a curve or a polygon.
- 2) Switch the selected object into editing points mode and open the Edit Points toolbar.
- 3) Click on **Insert Points** on the Edit Points toolbar.
- 4) Click on the object border to insert a point at the required position on the border.
- 5) Alternatively, click inside the object border to insert a point. The object automatically changes shape to include the new point into the object border.

Deleting points

Figure 38 shows what happens when three points on the left were deleted from a circle. The left image is a the full circle and the right image is where three points have been deleted creating a new shape.

- 1) Convert the object to a curve or a polygon.
- 2) Switch the selected object into editing points mode and open the Edit Points toolbar.
- 3) To delete a single point, proceed as follows
 - a) Select the point for deletion.
 - b) Click on **Delete Points** on the Edit Points toolbar.




Figure 38: Example of deleting points

- 4) To delete several points at the same time, proceed as follows:
 - a) Hold down the *Shift* key.
 - b) Select all the points for deletion.
 - c) Click on **Delete Points** on the Edit Points toolbar.

Eliminating points

The **Eliminate Points** tool on the Edit Points toolbar only functions on lines with multiple points. These lines are created when a curve is converted to a line using the **Convert to Curve** tool. An example of creating a straight line and eliminating points is shown in Figure 39.

- 1) Convert the curve to a curve or a polygon.
- 2) Switch the curve into editing points mode and open the Edit Points toolbar.
- 3) Select the curve with multiple points and convert to a line, see “Converting curves or lines” below.
- 4) Select the point or points on the line for elimination. The selected point is emphasized.
- 5) Select the **Eliminate Points** tool on the Edit Points toolbar.
- 6) Accurately position the cursor over the selected point, then click and drag the selected point. As the cursor is dragged, a dotted line forms between the neighboring points.
- 7) When this dotted line appears to be a straight line between the neighboring points, release the click. The selected point is eliminated and a straight line now exists between the neighboring points.

Converting curves or lines

Curves and lines are easily converted using the **Convert to Curve** tool on the Edit Points toolbar. When a curve is converted to a line, a straight line is created between selected points on a curve. When a line is converted to a curve, a curve is created between selected points on a line. An example of converting a curve to a line is shown in Figure 39.

- 1) Convert the object to a curve or a polygon.
- 2) Switch the object into editing points mode and open the Edit Points toolbar.




Figure 39: Example of converting a curve into a line

- 1) Curve with points displayed.
- 2) Sections between points converted to line.
- 3) Point deleted to create a line section.

- 3) Select the points for converting from curve to line or from line to curve.
- 4) Click on **Convert to Curve** on the Edit Points toolbar. Between the selected points, a curve is converted into a line or a line is converted into a curve.
- 5) Delete one of the points on the converted line to create a straight line.

Splitting objects

- 1) Convert the object to a curve or a polygon.
- 2) Switch the object into editing points mode and open the Edit Points toolbar.
- 3) Select the point or points on the object where it is to be split. Keep the *Shift* key pressed down when selecting more than one point.
- 4) Click on **Split Curve** on the Edit Points toolbar to split or cut the object border at the selected point. If the object is filled, it will be emptied because the object border is no longer closed, as shown in Figure 40.
- 5) Deselect the object, then drag the cut segment and move it away from the original object.

✓ Note

The point where the object was split is now larger than the remaining points visible on the object.

Closing objects

- 1) Select an open object (Figure 41).
- 2) Switch the object into editing points mode and open the Edit Points toolbar.
- 3) Select a point where the object has been split. Note that the start point of an object is larger than the other points visible on the object.




Figure 40: Example of splitting objects




Figure 41: Example of closing objects

- 4) Click on **Close Bézier** in the Edit Points toolbar to close the object. If the open object was originally a closed and filled object, then the original color fills the object when it is closed.

Distorting objects

- 1) Select the object and switch into editing points mode to display the points on the object. This also opens the Edit Points toolbar.
- 2) Select one of the points on the object and drag it to a new position to distort the object (Figure 42).




Figure 42: Example of distorting objects